

Powered by Universal Speech Solutions LLC



Asterisk and Bing SR

Usage Guide

Revision: 1

Created: October 30, 2017

Last updated: October 30, 2017

Author: Arsen Chaloyan

Table of Contents

1 Overview.....	4
1.1 Applicable Versions.....	4
2 Generic Speech Recognition API	5
2.1 Overview.....	5
2.2 Configuration Steps	5
2.3 Usage Example	5
3 Suite of UniMRCP Applications.....	7
3.1 Overview.....	7
3.2 Configuration Steps	7
3.3 Usage Example	8

1 Overview

This guide describes how to utilize the Microsoft Bing Speech services with Asterisk.



Note that the Asterisk and the UniMRCP server typically reside on different hosts in a LAN, although both might be installed on the same host.

Installation of the Asterisk and the UniMRCP server with the BingSR plugin is not covered in this document. Visit the corresponding web pages for more information.

<http://unimrcp.org/asterisk>
<http://unimrcp.org/bingsr>

1.1 Applicable Versions

Instructions provided in this guide are applicable to the following versions.



UniMRCP Modules for Asterisk 1.5.0 and above
UniMRCP BingSR Plugin 1.0.0 and above

2 Generic Speech Recognition API

2.1 Overview

The module *res_speech_unimrcp.so* provides an implementation of the Generic Speech Recognition API of Asterisk, based on the UniMRCP client library.

2.2 Configuration Steps

This section outlines major configuration steps required for use of the module *res_speech_unimrcp.so* with the UniMRCP server.

Check the name of the profile, referenced in the configuration file *res-speech-unimrcp.conf*, which is located in the configuration directory of Asterisk. Use *uni2* for MRCPv2, and *uni1* for MRCPv1.

```
[general]
unimrcp-profile = uni2 ; UniMRCP MRCPv2 Server
; unimrcp-profile = uni1 ; UniMRCP MRCPv1 Server
```

Open the configuration file *unimrcpclient.xml*, located in the configuration directory of UniMRCP and specify IP addresses of the client and the server. In the following example, the Asterisk/UniMRCP client is located on 10.0.0.1 and the UniMRCP server is on 10.0.0.2.

```
<properties>
  <!-- <ip type="auto"/> -->

  <ip>10.0.0.1</ip>
  <server-ip>10.0.0.2</server-ip>
</properties>
```

2.3 Usage Example

Make use of a built-in speech grammar *transcribe* for recognition, having no speech contexts defined, by adding the following entries in the Asterisk configuration file *extensions.conf*.

```
[sample-speech-transcription-1]
exten => s,1,Answer()
exten => s,2,SpeechCreate()
exten => s,3,SpeechActivateGrammar(builtin:speech/transcribe)
exten => s,4,SpeechBackground(beep, 20)
exten => s,5,Verbose(1, "Recognition result count: ${SPEECH(results)}")
```

```
exten => s,6,GotoIf(["${SPEECH(results)}" = "0"]?7:9)
exten => s,7,Playback(error)
exten => s,8,Goto(3)
exten => s,9,Verbose(1, "Recognition result: ${SPEECH_TEXT(0)}, confidence score:
${SPEECH_SCORE(0)}, grammar-uri: ${SPEECH_GRAMMAR(0)}")
exten => s,10,SpeechDestroy()
exten => s,11,Hangup()
```

In the Asterisk dialplan, associate the provided sample to an extension, for example, 700.

```
exten => 700,1,Goto(sample-speech-transcription-1,s,1)
```

Place a test call and make sure recognition works as expected.

3 Suite of UniMRCP Applications

3.1 Overview

The module *app_unimrcp.so* provides a suite of speech recognition and synthesis applications for Asterisk.

3.2 Configuration Steps

This section outlines major configuration steps required for use of the module *app_unimrcp.so* with the UniMRCP server.

Open the configuration file *mrcp.conf*, located in the configuration directory of Asterisk, and add two profiles for MRCPv2 and MRCPv1 respectively. In the following example, the Asterisk/UniMRCP client is located on 10.0.0.1 and the UniMRCP server is on 10.0.0.2.

```
[uni2]
; MRCP settings
version = 2
;
; SIP settings
server-ip = 10.0.0.2
server-port = 8060
; SIP user agent
client-ip = 10.0.0.1
client-port = 25097
sip-transport = udp
;
; RTP factory
rtp-ip = 10.0.0.1
rtp-port-min = 28000
rtp-port-max = 29000
;
; Jitter buffer settings
playout-delay = 50
max-playout-delay = 200
; RTP settings
ptime = 20
codecs = PCMU PCMA L16/96/8000 telephone-event/101/8000
; RTCP settings
rtcp = 0
```

```
[uni1]
```

```

; MRCP settings
version = 1
;
; RTSP settings
server-ip = 10.0.0.2
server-port = 1554
resource-location = media
speechsynth = speechsynthesizer
speechrecog = speechrecognizer;
;
; RTP factory
rtp-ip = 10.0.0.1
rtp-port-min = 27000
rtp-port-max = 28000
;
; Jitter buffer settings
playout-delay = 50
max-playout-delay = 200
; RTP settings
ptime = 20
codecs = PCMU PCMA L16/96/8000 telephone-event/101/8000
; RTCP settings
rtcp = 0

```

3.3 Usage Example

Make use of a built-in speech grammar *transcribe* for recognition, having no speech contexts defined, by adding the following entries in the Asterisk configuration file *extensions.conf*.

```

[sample-speech-transcription-2]
exten => s,1,Answer
exten => s,2,MRCPreco("built-in:speech/transcribe", spl=en-US&f=beep&p=uni2)
exten => s,3,Goto(mrcpreco-output,s,1)

```

Note the macro *mrcpreco-output*, used in the example above, is defined in the file *mrcp_sample_apps.conf*.

In the Asterisk dialplan, associate the provided sample to an extension, for example, 800.

```

exten => 800,1,Goto(sample-speech-transcription-2,s,1)

```

Place a test call and make sure recognition works as expected.