



Bing SR Plugin

Administrator Guide

Revision: 2

Distribution: Red Hat / Cent OS

Created: October 26, 2017

Last updated: January 26, 2018

Author: Arsen Chaloyan

Table of Contents

1 Overview.....	3
1.1 Applicable Versions.....	3
1.2 Supported Distributions	3
1.3 Authentication.....	3
2 Installing RPMs Using YUM.....	4
2.1 Repository Configuration	4
2.2 Repository Verification.....	4
2.3 BingSR Plugin Installation	5
3 Installing RPMs Manually	6
3.1 Package List.....	6
3.2 Package Installation Order	7
4 Obtaining License	8
4.1 License Type.....	8
4.2 Node Information.....	8
4.3 License Installation	8
5 Obtaining Service Subscription Keys	9
5.1 Bing Speech API Subscription.....	9
5.2 Subscription Key Installation.....	9
6 Configuring Server and Plugin	10
6.1 Plugin Factory Configuration	10
6.2 RTP Configuration.....	10
6.3 Logger Configuration	11
6.4 BingSR Plugin Configuration.....	11
7 Validating Setup.....	12
7.1 Launching Server.....	12
7.2 Launching Client.....	12

1 Overview

This guide describes how to obtain and install binary packages for the Microsoft Bing Speech Recognition (BingSR) plugin to the UniMRCP server on Red Hat-based Linux distributions. The document is intended for system administrators and developers.


1.1 Applicable Versions

Instructions provided in this guide are applicable to the following versions.

 UniMRCP 1.5.0 and above
UniMRCP BingSR Plugin 1.0.0 and above

1.2 Supported Distributions

UniMRCP binary packages are currently available only for x86_64 (64-bit) architecture.

Operating System	32-bit	64-bit
Red Hat / Cent OS 6		
Red Hat / Cent OS 7		

Note: packages for other distributions can be made available upon request. For more information, contact services@unimrcp.org.

1.3 Authentication

UniMRCP binary packages are available to authenticated users only. In order to register a free account with UniMRCP, please visit the following page.

 <https://www.unimrcp.org/profile-registration>

Note: a new account needs to be verified and activated prior further proceeding.

2 Installing RPMs Using YUM

Using the Yellowdog Updater, Modifier (yum), a command-line package management utility for Red Hat-based distributions, is recommended for installation of UniMRCP binary packages.

2.1 Repository Configuration

The content of a typical yum configuration file, to be placed in `/etc/yum.repos.d/unimrcp.repo`, is provided below.

```
[unimrcp]
name=UniMRCP Packages for Red Hat / Cent OS-$releasever $basearch
baseurl=https://username:password@unimrcp.org/repo/yum/main/rhel$releasever/$basearch/
enabled=1
sslverify=1
gpgcheck=1
gpgkey=https://unimrcp.org/keys/unimrcp-gpg-key.public

[unimrcp-noarch]
name=UniMRCP Packages for Red Hat / Cent OS-$releasever noarch
baseurl=https://username:password@unimrcp.org/repo/yum/main/rhel$releasever/noarch/
enabled=1
sslverify=1
gpgcheck=1
gpgkey=https://unimrcp.org/keys/unimrcp-gpg-key.public
```

The username and password fields included in the HTTPS URI must be replaced with the corresponding account credentials.

2.2 Repository Verification

In order to verify that yum can properly connect and access the UniMRCP repository, the following command can be used.

```
yum repolist unimrcp
yum repolist unimrcp-noarch
```

where *unimrcp* and *unimrcp-noarch* are names of the sections set in the yum configuration file above.

In order to retrieve a list of packages the UniMRCP repository provides, the following command can be used.

```
yum --disablerepo="*" --enablerepo="unimrcp" list available
```

```
yum --disablerepo="*" --enablerepo="unimrcp-noarch" list available
```

2.3 BingSR Plugin Installation

In order to install the BingSR plugin, including all the dependencies, use the following command.

```
yum install unimrcp-bing-sr
```

In order to install the additional data files for the sample client application *umc*, the following command can be used.

```
yum install umc-addons
```

Note: this package is optional and provides additional data which can be used for validation of basic setup.

3 Installing RPMs Manually

UniMRCP RPM packages can be installed manually using the *rpm* utility. Note, however, that the system administrator should take care of package dependencies and install all the packages in appropriate order.

The RPM packages have the following naming convention:

```
$packagename-$universion-$packageversion.el$rhelversion.$arch.rpm
```

where

- *packagename* is the name of a package
- *universion* is the UniMRCP version
- *packageversion* is the RPM release version
- *rhelversion* is the Red Hat version
- *arch* is the architecture (x86_64, i686, ...)

3.1 Package List

The following is a list of UniMRCP RPM packages required for the installation of the BingSR plugin.

Package Name	Description
unimrcp-bing-sr	BingSR plugin to the server.
unilibevent	UniMRCP edition of the libevent library.
umc-addons	Sample en-US data files used with umc. [Optional]
unilicnodegen	Node information retrieval tool, required for license deployment.
unimrcp-server	Shared library and application of the server.
unimrcp-client	Shared libraries and sample applications of the client. [Optional]
unimrcp-demo-plugins	Set of demo plugins to the server. [Optional]
unimrcp-common	Data common for the client and the server.
uniapr	UniMRCP edition of the Apache Portable Runtime (APR) library.

uniapr-util	UniMRCP edition of the Apache Portable Runtime Utility (APR-Util) library.
unisofia-sip	UniMRCP edition of the Sofia SIP library.

3.2 Package Installation Order

Note that all the RPM packages provided by UniMRCP are signed by a GNU Privacy Guard (GPG) key. Before starting the installation, you may need to import the public key in order to allow the *rpm* utility to verify the packages.

```
rpm --import https://unimrcp.org/keys/unimrcp-gpg-key.public
```

Packages for the APR, APR-Util and Sofia-SIP libraries must be installed first.

```
rpm -ivh uniapr-$aprversion-$packageversion.el$rhelversion.$sarch.rpm
rpm -ivh uniapr-util-$apuversion-$packageversion.el$rhelversion.$sarch.rpm
rpm -ivh unisofia-sip-$sofiaversion-$packageversion.el$rhelversion.$sarch.rpm
```

Then, a package containing common data for the client and the server, and a package for the server should follow.

```
rpm -ivh unimrcp-common-$universion-$packageversion.el$rhelversion.$sarch.rpm
rpm -ivh unimrcp-server-$universion-$packageversion.el$rhelversion.$sarch.rpm
```

Next, a package containing the utility tool *unilicnodegen*, required for license deployment.

```
rpm -ivh unilicnodegen-$toolversion-$packageversion.el$rhelversion.$sarch.rpm
```

Next, a package containing the libevent library.

```
rpm -ivh unilibevent-$libeventversion-$packageversion.el$rhelversion.$sarch.rpm
```

Finally, a package containing the BingSR plugin should follow.

```
rpm -ivh unimrcp-bing-sr-$universion-$packageversion.el$rhelversion.noarch.rpm
```

4 Obtaining License

The BingSR plugin to the UniMRCP server is a commercial product, which requires a license file to be installed.

4.1 License Type

The following license types are available:

- Trial
- Production
- Test and Development

4.2 Node Information

The license files are bound to a node the product is installed on. In order to obtain a license, the corresponding node information needs to be retrieved and submitted for generation of a license file.

Use the installed tool *unilicnodegen* to retrieve the node information.

```
/opt/unimrcp/bin/unilicnodegen
```

As a result, a text file *uninode.info* will be saved in the current directory. Submit the file *uninode.info* for license generation to services@unimrcp.org by mentioning the product name in the subject.

4.3 License Installation

The license file needs to be placed into the directory */opt/unimrcp/data*.

```
cp umsbingsr_*.lic /opt/unimrcp/data
```


5 Obtaining Service Subscription Keys

In order to utilize the Bing Speech API, a corresponding service subscription key needs to be retrieved from the Microsoft Cognitive Services portal and further installed to the UniMRCP server.

5.1 Bing Speech API Subscription

Subscribe to the Bing Speech API and obtain one of the keys.

1. Navigate to the Cognitive Service portal.
<https://azure.microsoft.com/try/cognitive-services/>
2. Select the Speech tab.
3. Click the Get API Key button for the Bing Speech API.
4. Accept and agree to the terms.
5. Log in to your account

As a result, the Bing Speech API will be added to your subscription with two keys available.

```
Endpoint: https://api.cognitive.microsoft.com/sts/v1.0  
Key 1: *****  
Key 2: *****
```

5.2 Subscription Key Installation

Copy one of the subscription keys and past the content into a text file *cognitive.subscription.key*, which needs to be placed to the directory */opt/unimrcp/data*.

```
printf 'one-of-your-keys' > /opt/unimrcp/data/cognitive.subscription.key
```

Note that the file *cognitive.subscription.key* must NOT contain any additional preceding or trailing characters, besides the key itself.

6 Configuring Server and Plugin

6.1 Plugin Factory Configuration

In order to load the BingSR plugin into the UniMRCP server, open the file *unimrcpserver.xml*, located in the directory */opt/unimrcp/conf*, and add the following entry under the XML element *<plugin-factory>*. Disable other recognition plugins, if available. The remaining demo plugins might also be disabled, if not installed.

```
<!-- Factory of plugins (MRCP engines) -->
<plugin-factory>
  <engine id="Demo-Synth-1" name="demosynth" enable="true"/>
  <engine id="Demo-Recog-1" name="demorecog" enable="false"/>
  <engine id="Demo-Verifier-1" name="demoverifier" enable="true"/>
  <engine id="Recorder-1" name="mrcprecorder" enable="true"/>
  <engine id="Bing-SR-1" name="umsbingsr" enable="true"/>
</plugin-factory>
```

6.2 RTP Configuration

Since the Bing Speech API supports PCM audio sampled at 16 kHz only, the corresponding codecs needs to be specified in the configuration file *unimrcpserver.xml* under the XML element *<rtp-settings>* as follows.

```
<rtp-settings id="RTP-Settings-1">
  <codecs own-preference="false">PCMU/97/16000 PCMA/98/16000 L16/99/16000
    telephone-event/102/16000</codecs>
</rtp-settings>
```

For the basic verification test to work, similar settings should be specified in the client configuration file *unimrcpclient.xml* as well.

```
<rtp-settings id="RTP-Settings-1">
  <codecs>PCMU PCMA L16/96/8000 telephone-event/101/8000 PCMU/97/16000
    PCMA/98/16000 L16/99/16000 telephone-event/102/16000</codecs>
</rtp-settings>
```

6.3 Logger Configuration

In order to enable log output from the plugin and set filtering rules, open the configuration file *logger.xml*, located in the directory */opt/unimrcp/conf*, and add the following entry under the element *<sources>*.

```
<source name="BINGSR-PLUGIN" priority="INFO" masking="NONE"/>
```

6.4 BingSR Plugin Configuration

The configuration file of the plugin is located in */opt/unimrcp/conf/umsbingsr.xml*. Default settings should be sufficient for generic use.

Refer to the *Usage Guide* for more information.

7 Validating Setup

Validate your setup by using the sample UniMRCP client and server applications on the same host. The default configuration and data files should be sufficient for a basic test.

7.1 Launching Server

Launch the UniMRCP server application.

```
cd /opt/unimrcp/bin
./unimrcpserver
```

In the server log output, check whether the plugin is normally loaded.

```
[INFO] Load Plugin [Bing-SR-1] [/opt/unimrcp/plugin/umsbingsr.so]
```

Next, check for the license information.

```
[NOTICE] UniMRCP BINGSR License

-product name:  umsbingsr
-product version: 1.0.0
-license owner:  -
-license type:   trial
-issue date:    2017-10-26
-exp date:     2017-11-25
-channel count: 2
-feature set:   0
```

7.2 Launching Client

Note: the optional package *umc-addons* must be installed for this test to work.

Launch the sample UniMRCP client application *umc*.

```
cd /opt/unimrcp/bin
./umc
```

Run a typical speech recognition scenario by issuing the command *run bsr1* from the console of the *umc* client application.

```
run bsr1
```

This command sends a RECOGNIZE request to the server and then starts streaming a sample audio input file *whatstheweatherlike.pcm* to recognize.

Check for the NLSML results to be returned as expected.

```
<?xml version="1.0"?>
<result>
  <interpretation grammar="builtin:speech/transcribe" confidence="0.95">
    <instance>what's the weather like</instance>
    <input mode="speech">what's the weather like</input>
  </interpretation>
</result>
```

Visually inspect the log output for any possible warnings or errors.

Note that utterances are stored in the *var* directory, if the corresponding parameter is enabled in the configuration file *umsbingsr.xml* and/or requested by the client.