

Powered by Universal Speech Solutions LLC



Google Speech Recognition Plugin

Administrator Guide

Revision: 1

Distribution: Debian / Ubuntu

Created: May 16, 2017

Last updated: May 16, 2017

Author: Arsen Chaloyan

Table of Contents

1	Overview.....	3
1.1	Applicable Versions.....	3
1.2	Supported Distributions	3
1.3	Authentication.....	3
2	Installing Deb Packages Using Apt-Get	4
2.1	Repository Configuration	4
2.2	GnuPG Key.....	4
2.3	Repository Update	4
2.4	GSR Plugin Installation	4
3	Installing Deb Packages Manually.....	6
3.1	Package List.....	6
3.2	Package Installation Order.....	7
4	Obtaining License	8
4.1	License Type.....	8
4.2	Node Information.....	8
4.3	License Installation	8
5	Obtaining Service Credentials	9
5.1	Project Creation	9
5.2	Project Billing	9
5.3	Speech API	9
5.4	Credentials Retrieval.....	9
5.5	Credentials Installation	10
6	Configuring Server and Plugin	11
6.1	Plugin Factory Configuration	11
6.2	Logger Configuration	11
6.3	GSR Plugin Configuration.....	11
7	Validating Setup.....	12
7.1	Launching Server.....	12
7.2	Launching Client.....	12

1 Overview

This guide describes how to obtain and install binary packages for the Google Speech Recognition (GSR) plugin to the UniMRCP server on Debian-based Linux distributions. The document is intended for system administrators and developers.


1.1 Applicable Versions

Instructions provided in this guide are applicable to the following versions.

 UniMRCP 1.4.0 and above
UniMRCP GSR Plugin 1.0.0 and above

1.2 Supported Distributions

UniMRCP binary packages are currently available only for x86_64 (64-bit) architecture.

Operating System	32-bit	64-bit
Ubuntu 14.04 LTS (trusty)		
Ubuntu 16.04 LTS (xenial)		

Note: packages for other distributions can be made available upon request. For more information, contact services@unimrcp.org.

1.3 Authentication

UniMRCP binary packages are available to authenticated users only. In order to register a free account with UniMRCP, please visit the following page.

 <https://www.unimrcp.org/profile-registration>

Note: a new account needs to be verified and activated prior further proceeding.

2 Installing Deb Packages Using Apt-Get

Using the APT package handling utility (`apt-get`) is recommended for installation of UniMRCP binary packages.

2.1 Repository Configuration

The content of a typical configuration file of the APT repository, to be placed in `/etc/apt/sources.list.d/unimrcp.list`, is provided below.

```
deb [arch=amd64] https://username:password@unimrcp.org/repo/apt/ distr main
```

The *username* and *password* fields included in the HTTPS URI must be replaced with the corresponding account credentials.

The *distr* field must be replaced with the corresponding distribution code name such as *trusty*, *xenial*, etc.

2.2 GnuPG Key

For verification of binary packages, UniMRCP provides a public GnuPG key, which can be retrieved and installed as follows.

```
wget -O - https://unimrcp.org/keys/unimrcp-gpg-key.public | sudo apt-key add -
```

2.3 Repository Update

In order to check for updates and apply the changes in the APT configuration, use the following command.

```
sudo apt-get update
```

2.4 GSR Plugin Installation

In order to install the GSR plugin, including all the dependencies, use the following command.

```
sudo apt-get install unimrcp-gsr
```

As a result, *apt-get* will check and prompt to download all the required packages by installing them in the directory `/opt/unimrcp`.

In order to install the additional data files for the sample client application *umc*, the following command can be used.

```
sudo apt-get install umc-addons
```

Note: this package is optional and provides additional data which can be used for validation of basic setup.

3 Installing Deb Packages Manually

UniMRCP deb packages can be installed manually using the *dpkg* utility. Note, however, that the system administrator should take care of package dependencies and install all the packages in appropriate order.

The deb packages have the following naming convention:

```
$packagename_${universion}-${distr}_${arch}.deb
```

where

- *packagename* is the name of a package
- *universion* is the UniMRCP version
- *distr* is the distribution code name (trusty, xenial, ...)
- *arch* is the architecture (amd64, i386, all, ...)

3.1 Package List

The following is a list of UniMRCP deb packages required for the installation of the GSR plugin.

Package Name	Description
unimrcp-gsr	GSR plugin to the server.
unigrpc	UniMRCP edition of the gRPC library.
umc-addons	Sample en-US data files used with umc. [Optional]
unilicnodegen	Node information retrieval tool, required for license deployment.
unimrcp-server	Shared library and application of the server.
unimrcp-client	Shared libraries and sample applications of the client. [Optional]
unimrcp-demo-plugins	Set of demo plugins to the server. [Optional]
unimrcp-common	Data common for the client and the server.
uniapr	UniMRCP edition of the Apache Portable Runtime (APR) library.

uniapr-util	UniMRCP edition of the Apache Portable Runtime Utility (APR-Util) library.
unisofia-sip	UniMRCP edition of the Sofia SIP library.

3.2 Package Installation Order

Packages for APR, APR-Util and Sofia-SIP libraries must be installed first.

```
sudo dpkg --install uniapr_${aprversion}-${distr}_${arch}.deb
sudo dpkg --install uniapr-util_${apuverson}-${distr}_${arch}.deb
sudo dpkg --install unisofia-sip_${sofiaversion}-${distr}_${arch}.deb
```

Then, a package containing common data for the client and the server, and a package for the server should follow.

```
sudo dpkg --install unimrcp-common_${universion}-${distr}_${arch}.deb
sudo dpkg --install unimrcp-server_${universion}-${distr}_${arch}.deb
```

Next, a package containing the utility tool *unilicnodegen*, required for license deployment.

```
sudo dpkg --install unilicnodegen_${stoolversion}-${distr}_${arch}.deb
```

Next, a package containing the gRPC library.

```
sudo dpkg --install unigrpc_${grpcversion}-${distr}_${arch}.deb
```

Finally, a package containing the GSR plugin should follow.

```
sudo dpkg --install unimrcp-gsr_${universion}-${distr}_all.deb
```

4 Obtaining License

The GSR plugin to the UniMRCP server is a commercial product, which requires a license file to be installed.

4.1 License Type

The following license types are available:

- Trial
- Production
- Test and Development

4.2 Node Information

The license files are bound to a node the product is installed on. In order to obtain a license, the corresponding node information needs to be retrieved and submitted for generation of a license file.

Use the installed tool *unilicnodegen* to retrieve the node information.

```
sudo /opt/unimrcp/bin/unilicnodegen
```

As a result, a text file *uninode.info* will be saved in the current directory. Submit the file *uninode.info* for license generation to services@unimrcp.org by mentioning the product name in the subject.

4.3 License Installation

The license file needs to be placed into the directory */opt/unimrcp/data*.

```
sudo cp umsgsr_*.lic /opt/unimrcp/data
```


5 Obtaining Service Credentials

In order to utilize the Google Cloud Speech API, a corresponding service account credentials need to be retrieved from the Google Cloud Platform Console and further installed to the UniMRCP server.

5.1 Project Creation

Create a project in the Google Cloud Platform Console, if not already created. Projects allow to manage all Google Cloud Platform resources, including deployment, access control, billing, and services.

1. Open the Cloud Platform Console.
<https://console.cloud.google.com>
2. In the drop-down menu at the top, select a project *My First Project* created by default or create a new project.

5.2 Project Billing

Enable billing for your project, if not already enabled. Enabling billing allows the application to consume billable resources such as Speech API calls. See Cloud Platform Console Help for more information about billing settings.

5.3 Speech API

In the Google Cloud Platform Console, navigate to API Manager and enable the Speech API.

As for the Speech API version, the GSR plugin utilizes *v1*. Since all API versions (*v1* and *v1beta*) are selected by default, no action is required.

5.4 Credentials Retrieval

Download service account credentials file.

1. In the Google Cloud Platform Console, navigate to API Manager > Credentials > Create credentials > Service account key
2. Under **Service account**, select *New service account*.
3. Under **Service account name**, enter a service account name of your choice. For example, *transcriber*.
4. Under **Role**, select Project > Service Account Actor.
5. Under **Key type**, leave JSON selected.

6. Click **Create** to create a new service account and download the json credentials file.

5.5 Credentials Installation

The downloaded json credentials file needs to be placed into the directory `/opt/unimrcp/data`.

```
sudo cp *.json /opt/unimrcp/data
```

6 Configuring Server and Plugin

6.1 Plugin Factory Configuration

In order to load the GSR plugin into the UniMRCP server, open the file *unimrcpserver.xml*, located in the directory */opt/unimrcp/conf*, and add the following entry under the XML element *<plugin-factory>*. Disable other recognition plugins, if available. The remaining demo plugins might also be disabled, if not installed.

```
<!-- Factory of plugins (MRCP engines) -->
<plugin-factory>
  <engine id="Demo-Synth-1" name="demosynth" enable="true"/>
  <engine id="Demo-Recog-1" name="demorecog" enable="false"/>
  <engine id="Demo-Verifier-1" name="demoverifier" enable="true"/>
  <engine id="Recorder-1" name="mrcpreorder" enable="true"/>
  <engine id="GSR-1" name="umsgsr" enable="true"/>
</plugin-factory>
```

6.2 Logger Configuration

In order to enable log output from the plugin and set filtering rules, open the configuration file *logger.xml*, located in the directory */opt/unimrcp/conf*, and add the following entry under the element *<sources>*.

```
<source name="GSR-PLUGIN" priority="INFO" masking="NONE"/>
```

6.3 GSR Plugin Configuration

The configuration file of the plugin is located in */opt/unimrcp/conf/umsgsr.xml*. Default settings should be sufficient for generic use.

Refer to the *Usage Guide* for more information.

7 Validating Setup

Validate your setup by using the sample UniMRCP client and server applications on the same host. The default configuration and data files should be sufficient for a basic test.

7.1 Launching Server

Launch the UniMRCP server application.

```
cd /opt/unimrcp/bin  
sudo ./unimrcpserver
```

In the server log output, check whether the plugin is normally loaded.

```
[INFO] Load Plugin [GSR-1] [/opt/unimrcp/plugin/umsgsr.so]
```

Next, check for the license information.

```
[NOTICE] UniMRCP GSR License  
  
-product name:  umsgsr  
-product version: 1.0.0  
-license owner:  Name  
-license type:   trial  
-issue date:    2017-05-11  
-exp date:     2017-06-10  
-channel count: 2  
-feature set:   0
```

Next, check for the service account credentials.

```
[NOTICE] Set Google App Credentials /opt/unimrcp/data/My First Project-a78...c15.json
```

7.2 Launching Client

Open the configuration file `/opt/unimrcp/conf/umscenarios.xml` and add a new section corresponding to the use with the GSR plugin.

```
<scenario name="gsr" class="Recognizer" profile="uni2">  
  <resource-discovery enable="0"/>
```

```
<define-grammar enable="0"/>
<recognize enable="1" content-type="text/uri-list" content-location="jgrammar.list" audio-
  source="callsteve.pcm"/>
<termination enable="1">
  <capabilities>
    <codec name="LPCM" rates="8000 16000"/>
  </capabilities>
</termination>
</scenario>
```

Launch the sample UniMRCP client application *umc*.

```
cd /opt/unimrcp/bin
./umc
```

Run a typical speech recognition scenario by issuing the command *run gsr* from the console of the *umc* client application.

```
run gsr
```

This command sends a RECOGNIZE request to the server and then starts streaming a sample audio input file *callsteve.pcm* to recognize.

Check for the NLSML results to be returned as expected.

```
<?xml version="1.0"?>
<result>
  <interpretation grammar="command" confidence="0.92">
    <instance>call Steve</instance>
    <input mode="speech">call Steve</input>
  </interpretation>
</result>
```

Visually inspect the log output for any possible warnings or errors.

Note that utterances are stored in the *var* directory, if the corresponding parameter is enabled in the configuration file *umsgsr.xml* and/or requested by the client.